



# WorkPacket

# WorkPacket Related













Mosaix™

**LEGEND**

Refer to Page 8


Chart Version 1.0

# Catalog Related




# Session Control

## Session Related




# Control Related

Note: All controls have Refresh and Clear methods.



Note: RecordSetDataList on page 8.


**RecordSetListView**  
 Events: Click(), DbClick().




**EBPI: BPIRecordSet**  
**CBPI: RecordSet**

- .Count
- .Template



**CatalogSetTreeView**  
 Events: DbClick()




**WorklistsListView or WorklistsComboView** Events: Click()




**WorkList**



**AttributeView**  
 Events: FieldLostFocus (IIndex, IAllowChange), FieldSetFocus (IIndex)




**MemoView**  
 Note: No Refresh method



**FolderListView**

Events: Click(), DbClick(), SelChange(), FolderChanged(), CustomizeDescription (sDescr, oPict, oFI, IIndex)



Mosaix™

**LEGEND**


Refer to Page 8

Chart Version 1.0


# DocumentView

Related



**DocumentView** Events: DocumentChanged(), PageChanged()  
 EBPI Only: BeforeLayer(oMarkups), SavingMarkups(oMarkups)




Possible Action Values	
bpiCopy	= 3
bpiCropPage	= 7
bpiCut	= 2
bpiDelete	= 5
bpiDuplicate	= 6
bpiPaste	= 4
bpiRotate	= 9
bpiUncropPage	= 8
bpiZoomToPrevious	= 10




Possible Mode Values	
bpiZoom	= 10
bpiBitMap	= 11
bpiSelect	= 13
bpiCrop	= 12
bpiRectangle	= 14
bpiLine	= 20
bpiOval	= 21
bpiPolyline	= 18
bpiScribble	= 17
bpiText	= 16
bpiHilite	= 14
bpiPostit	= 15



# Workflow Related




**lErrLevel:**  
 bpiError = Error,  
 bpiWarning = Warning,  
 bpiMessage = Normal Message,  
 bpiMessage1 = Message, Level 1  
 bpiMessage2 = Message, Level 2  
 bpiMessage3 = Message, Level 3  
 bpiMessage4 = Message, Level 4



**WorkflowAccess**  
 Events: BeforeOpen(), AfterOpen(), BeforeClose(), AfterClose(), BeforeForward(), AfterForward(), CurrentWorklistChanged(), CurrentWorkpacketChanged(), ForwardError (lErrCode, sDescr, \*lResponse), CloseError (lErrCode, sDescr, \*lResponse), OpenError (lErrCode, sDescr, \*lResponse)  
 Note: lResponse is: 0 = Don't Display, 1 = Display Error

Note: Design Setup Time Only.  
 WorkflowInfo is OLE creatable at runtime.







Mosaix™

**LEGEND**  
 Refer to Page 8 Chart Version 1.0



# RapidStart

## Ready Foundation



**Data**

- s RF\_GetData(oPropertySet, sField)
- s RF\_GetProperty(Item, sProperty, [sPSName], [IVUNum])
- o RF\_GetPropertySet(Item, [sPSName], [IVUNum])
- b RF\_SetProperty(Item, sName, vValue, [vPage], [IVUNum])
- b RF\_SetPropertyData(Item, cData, [sPSName], [IVUNum])

**Markups & Display**

- RF\_MarkupOptions ([IVUNum])
- RF\_PenSize (IPen, [IVUNum])
- b RF\_RotateImage(Rotation, [IVUNum])
- b RF\_SetViewerMode(Mode, [IVUNum])
- RF\_ZoomSetup ([IVUNum])

**Open Workpacket**

- l RF\_GetOpenMode([IVUNum])
- b RF\_SetOpenMode(OpenMode, [IVUNum])
- l RF\_OpenWorkpacket([sWorklist], [oCriteria], [IVUNum])  If in popup mode

**Move Workpacket**

- b RF\_CloseWorkpacket(sMode, [IVUNum])
- b RF\_ForwardWorkpacket(sButtonClick, [IVUNum])
- b RF\_HoldWorkpacket(sButtonClick, [IVUNum])
- b RF\_RejectWorkpacket(sButtonClick, [IVUNum])
- b RF\_DeleteWorkpacket([IVUNum])
- i RF\_DeleteDocuments(cDelete, [IVUNum])

**Attributes**

- b RF\_CheckAttributes([IVUNum])  if error
- b RF\_CopyAttributes(cMakeSame, [IVUNum])
- b RF\_LockAttributes(cFields, [IVUNum])
- b RF\_MapAttributes(IDocNum, ITarget, [cMakeSame], [IVUNum])
- b RF\_ReadOnlyAttributes(sName, [IVUNum])
- b RF\_SetAttributeViewValue(sName, vValue, [IVUNum])

**Types**

- RF\_ClearTypes()
- b RF\_ChangeCurrentType(sTypeDescription, [IVUNum])
- c RF\_QueryTypes(sPrefix)
- o RF\_TypeCurrentDefaults([IVUNum])
- s RF\_TypeCurrentDescription([IVUNum])
- s RF\_TypeCurrentName([IVUNum])
- o RF\_TypeDefaults(sTypeName)
- s RF\_TypeDescription(sTypeName)
- s RF\_TypeGetDefault(sAttributeName, sTypeDescription)
- s RF\_TypeName(sTypeDescription)

**Views**

- b RF\_RegisterView([IVUNum, IVUMode, oRole])
- b RF\_CloseView(sMode, [IVUNum])
- b RF\_RefreshAllControls([IVUNum])
- l RF\_TotalDocs([IVUNum])
- b RF\_UpdateDoc([IVUNum])
- b RF\_DefineView(oViewer, oWFAccess, oFLV, [oAttributeView, oMemoView])
- b RF\_RegisterPBView([IVUNum, IVUMode, cCls])

**Print and fax**

- b RF\_FaxWorkpacket([IVUNum])
- b RF\_PrintWorkpacket([IVUNum])
- b RF\_FaxDocuments(cDocs, [IVUNum])
- b RF\_PrintDocuments(cDocs, [IVUNum])

**Contents**

- b RF\_ErrorMgr(oErrMgr)
- o RF\_Folder([IVUNum])
- o RF\_FolderItem(vDocNum, [IVUNum])
- o RF\_Workpacket([IVUNum])
- l RF\_CurrentDoc([IVUNum])

**Navigation**


- b RF\_GotoDocument(IDocNum, [IVUNum])
- b RF\_LaunchDocument(IDocNum, [IVUNum])
- s RF\_NextDoc([IVUNum])
- s RF\_NextPage([IVUNum])
- l RF\_NextPosition()
- s RF\_PreviousDoc([IVUNum])
- s RF\_PreviousPage([IVUNum])
- b RF\_ShowDocument(IDocNum, [IVUNum])
- b RF\_ShowPage(PageNum, [IVUNum])
- s RF\_DocumentStatus([IVUNum])
- s RF\_PageStatus([IVUNum])
- b RF\_GotoFolder([IVUNum])

- s .RF\_AppIniName()
- s .RF\_AppIniPath()
- .RF\_CenterForm (fForm)
- .RF\_ChangeOwners (oUIManager)
- b .RF\_ChangePassword(oSessionObj)
- .RF\_ClearGroups()
- .RF\_ClearUsers()
- .RF\_ConfigEditor(oUIManager, oVuMgr)
- s .RF\_DecodePassword(sCodedString)
- s .RF\_GetGroupIdFromName(sGroupName)
- s .RF\_GetGroupNameFromId(sGroupID)
- s .RF\_GetDBName

- s .RF\_GetODBCInfo()
- c .RF\_GetSessionInformation(sCommandLine)
- s .RF\_GetString(iNumber, [vOpt1, ..., vOpt11])
- s .RF\_GetUserIdFromName(sUserName)
- s .RF\_GetUserNameFromId(sUserID)
- b .RF\_PairList(oColl, sName, vValue)
- l .RF\_ParseIniString(sString, \*aStrings())
- c .RF\_QueryAllGroups()
- c .RF\_QueryAllGroupUserList()
- c .RF\_QueryAllUsers()
- c .RF\_QueryAllUsersInGroup(sGroupID)
- .RF\_LocateWorkpacket(oUIMgr, oVuMgr)

- c .RF\_ParseList(wString, Separator)
- c .RF\_QueryMyGroupIds(sUserID)
- c .RF\_QueryMyGroups(sUserID)
- c .RF\_QueryMyGroupUserList(sUserID)
- .RF\_QueueMonitor(oUIMgr)
- s .RF\_ReadIni(sSection, sEntry, [sPath])
- c .RF\_ReadIniSection(sSection, \*aStrings[, sPath])
- s .RF\_RootAppend(sPath, sRoot)
- a .RF\_SearchSettings()
- s .RF\_SystemIniPath()
- a .RF\_TypeSearchCriteria(sUserID)
- s .RF\_Version()
- s .RF\_ShowHistory(oWorkpacket)

- b .RF\_ErrorAddResource(iErrNum, sModName, sRoutine, iDebugLevel, [vOpt1, vOpt2, vOpt3, vOpt4, vOpt5])
- b .RF\_ErrorAddString(iErrNum, sErrMsg, sModuleName, sRoutine, iDebugLevel)
- .RF\_ErrorClear()
- b .RF\_ErrorInit()
- l .RF\_ErrorShowDialog(vClear, vButtons, vTitle, vMsg, vIcon)
- l .RF\_LogMessage(sMessage, iDebugLevel)
- b .RF\_LogSetFile(sFilePath, iKeepFiles, iMaxFileSize, iDebugLevel)







Mosaix™

LEGEND

Refer to Page 8

Chart Version 1.0



# Other

